Package 'mrgsolve'

January 23, 2019

Type Package

Version 0.9.0

Title Simulate from ODE-Based Models

Maintainer Kyle T Baron <kyleb@metrumrg.com>

URL https://github.com/metrumresearchgroup/mrgsolve

BugReports https://github.com/metrumresearchgroup/mrgsolve/issues

Description Fast simulation from ordinary differential equation (ODE) based models typically employed in quantitative pharmacology and systems biology.

License GPL (>= 2)

Depends R (>= 3.1.2), methods

Imports Rcpp (>= 0.12.12), dplyr (>= 0.7.8), magrittr (>= 1.5), RcppArmadillo (>= 0.7.900.2.0), tibble (>= 1.2), rlang (>= 0.3.0.1)

LinkingTo Rcpp (>= 0.12.12), RcppArmadillo (>= 0.7.900.2.0), BH (>= 1.62.0-1)

Suggests lattice, testthat, xml2 (>= 1.2.0), rmarkdown

LazyLoad yes

NeedsCompilation yes

Encoding UTF-8

Collate 'RcppExports.R' 'utils.R' 'package.R' 'generics.R' 'class_tgrid.R' 'class_numericlist.R' 'class_matlist.R' 'class_ev.R' 'class_derived.R' 'class_mrgmod.R' 'class_mrgsims.R' 'Aaaa.R' 'annot.R' 'chain.R' 'class_build.R' 'events.R' 'class_rx.R' 'compile.R' 'data_set.R' 'datasets.R' 'env.R' 'funset.R' 'idata_set.R' 'init.R' 'inven.R' 'knobs.R' 'matlist.R' 'matrix.R' 'mcode.R' 'model_include.R' 'modlib.R' 'modspec.R' 'mread.R' 'mrgindata.R' 'mrgsim_q.R' 'mrgsims.R' 'mrgsolve.R' 'nmxml.R' 'param.R' 'print.R' 'qsim.R' 'realize_addl.R' 'relabel.R' 'render.R' 'update.R' 'workflows.R'

RoxygenNote 6.1.1

Author Kyle T Baron [aut, cre] (<https://orcid.org/0000-0001-7252-5656>),
Alan C Hindmarsh [ctb],
Linda R Petzold [ctb],
Bill Gillespie [ctb],
Charles Margossian [ctb],
Devin Pastoor [ctb],
Bill Denney [ctb] (<https://orcid.org/0000-0002-5759-428X>),
Metrum Research Group [cph]

Repository CRAN

Date/Publication 2019-01-23 16:40:03 UTC

R topics documented:

---

aboutsolver *About the ODEPACK differential equation solver used by mrgsolve*

Description

About the ODEPACK differential equation solver used by mrgsolve

DLSODA

```
C-----------------------------------------------------------------------
C This is the 12 November 2003 version of
C DLSODA: Livermore Solver for Ordinary Differential Equations, with
C         Automatic method switching for stiff and nonstiff problems.
C
C This version is in double precision.
C
C DLSODA solves the initial value problem for stiff or nonstiff
C systems of first order ODEs,
C     dy/dt = f(t,y) ,  or, in component form,
C     dy(i)/dt = f(i) = f(i,t,y(1),y(2),...,y(NEQ)) (i = 1,...,NEQ).
C
C This a variant version of the DLSODE package.
C It switches automatically between stiff and nonstiff methods.
C This means that the user does not have to determine whether the
C problem is stiff or not, and the solver will automatically choose the
C appropriate method.  It always starts with the nonstiff method.
C
C Authors:       Alan C. Hindmarsh
C                Center for Applied Scientific Computing, L-561
C                Lawrence Livermore National Laboratory
C                Livermore, CA 94551
C and
C                Linda R. Petzold
C                Univ. of California at Santa Barbara
C                Dept. of Computer Science
C                Santa Barbara, CA 93106
C
C References:
C 1.  Alan C. Hindmarsh,  ODEPACK, A Systematized Collection of ODE
C     Solvers, in Scientific Computing, R. S. Stepleman et al. (Eds.),
C     North-Holland, Amsterdam, 1983, pp. 55-64.
C 2.  Linda R. Petzold, Automatic Selection of Methods for Solving
C     Stiff and Nonstiff Systems of Ordinary Differential Equations,
C     Siam J. Sci. Stat. Comput. 4 (1983), pp. 136-148.
C-----------------------------------------------------------------------
```

as.ev *Coerce an object to class ev*

Description

Coerce an object to class ev

Usage

```
as.ev(x, ...)

## S4 method for signature 'data.frame'
as.ev(x, keep_id = TRUE, clean = FALSE, ...)

## S4 method for signature 'ev'
as.ev(x, ...)
```

Arguments

x	an object to coerce
...	not used
keep_id	if TRUE, ID column is retained if it exists
clean	if TRUE, only dosing or ID information is retained in the result

Examples

```
data <- data.frame(amt = 100)

as.ev(data)
```

as.list,mrgmod-method *Coerce a model object to list*

Description

Coerce a model object to list

Usage

```
## S4 method for signature 'mrgmod'
as.list(x, deep = FALSE, ...)
```

Arguments

x	mrgmod object
deep	if TRUE, extra information is returned (see details).
...	not used

Details

If deep is TRUE, then the values for trans,advan, and mindt are returned as well as a summary of internal model functions (with a call to mrgsolve:::funset).

Slots

- npar: number of parameters
- neq: number of compartments or differential equations
- pars: names of model parameters
- covariates: names of parameters identified as covariates
- cmt: names of model compartments
- param: the parameter list
- init: initial condition list
- omega: $OMEGA matrices, as a matlist object
- sigma: $SIGMA matrices, as a matlist object
- fixed: named list of $FIXED values
- model: model name
- project: model project directory
- soloc: directory where the model is being built
- sodll: complete path to the model shared object
- cfile: path for the model source code file
- shlib: list of compilation information
- start: simulation start time
- end: simulation end time
- delta: simulation time step
- add: additional simulation times
- capture: names of captured data items
- random: names and labels of $OMEGA and $SIGMA
- code: model source code from cfile
- details: model details data frame
- atol: see solversettings
- rtol: see solversettings
- maxsteps: see solversettings

- `hmin`: see solversettings
- `hmax`: see solversettings
- `envir`: the model environment
- `plugins`: plugins invoked in the model
- `digits`: number of digits to request in simulated data
- `request`: compartments requested upon simulation
- `tscale`: multiplicative scalar for time in results only
- `mindt`: simulation output time below which there model will assume to have not advanced
- `preclean`: logical indicating to clean up compilation artifacts prior to compiling
- `debug`: print debugging information during simulation run
- `verbose`: print extra information during setup for model run

`as.list,mrgsims-method` *Coerce an mrgsims object to list*

Description

Coerce an mrgsims object to list

Usage

```
## S4 method for signature 'mrgsims'
as.list(x, ...)
```

Arguments

`x`	an mrgsims object
`...`	not used

`as_bmat` *Coerce R objects to block or diagonal matrices*

Description

These are simple functions that may be helpful to create the matrix objects that mrgsolve expects. Functions are named based on whether they create a diagonal matrix (`d`), a block matrix (`b`), or a a correlation matrix (`c`).

Usage

```
as_bmat(x, ...)

## S4 method for signature 'list'
as_bmat(x, ...)

## S4 method for signature 'numeric'
as_bmat(x, pat = "*", ...)

## S4 method for signature 'data.frame'
as_bmat(x, pat = "*", cols = NULL, ...)

## S4 method for signature 'ANY'
as_bmat(x, ...)

as_dmat(x, ...)

## S4 method for signature 'list'
as_dmat(x, ...)

## S4 method for signature 'ANY'
as_dmat(x, ...)

## S4 method for signature 'numeric'
as_dmat(x, pat = "*", ...)

## S4 method for signature 'data.frame'
as_dmat(x, pat = "*", cols = NULL, ...)

as_cmat(x, ...)
```

Arguments

x	data frame or list
...	arguments passed to dmat or bmat
pat	regular expression, character
cols	column names to use instead of pat

Details

Use as_dmat to create a diagonal matrix, as_bmat to create a block matrix, and as_cmat to create a block matrix where diagonal elements are understood to be correlations rather than covariances. as_cmat uses as_bmat to form the matrix and then converts off-diagonal elements to covariances before returning.

The methods for data.frame will work down the rows of the data frame and make the appropriate matrix from the data in each row. The result is a list of matrices.

Value

A numeric matrix for list and numeric methods. For data.frames, a list of matrices are returned.

See Also

bmat, dmat, cmat

Examples

```
df <- data.frame(
  OMEGA1.1 = c(1,2),
  OMEGA2.1 = c(11,22),
  OMEGA2.2 = c(3,4),
  SIGMA1.1 = 1,
  FOO=-1
)

as_bmat(df, "OMEGA")
as_dmat(df,"SIGMA")
as_dmat(df[1,],"OMEGA")
```

---

as_data_set *Create a simulation data set from ev objects*

Description

Create a simulation data set from ev objects

Usage

```
as_data_set(x, ...)

## S4 method for signature 'ev'
as_data_set(x, ...)

## S4 method for signature 'data.frame'
as_data_set(x, ...)
```

Arguments

x	ev objects
...	more ev objects

Details

The goal is to take a series of event objects and combine them into a single data set that can be passed to data_set. Each event object is added to the data frame as an ID or set of IDs that are distinct from the IDs in the other event objects. Note that including ID argument to the ev call where length(ID) is greater than one will render that set of events for all of IDs that are requested.

To get a data frame with one row (event) per ID look at expand.ev.

Value

a data frame suitable for passing into data_set

Examples

```
as_data_set(ev(amt=c(100,200), cmt=1, ID=1:3),
            ev(amt=300, time=24, ID=1:2),
            ev(amt=1000, ii=8, addl=10, ID=1:3))

# Instead of this, use expand.ev
as_data_set(ev(amt=100), ev(amt=200),ev(amt=300))
```

---

as_deslist *Create a list of designs from a data frame*

Description

Create a list of designs from a data frame

Usage

```
as_deslist(data, descol = "ID")
```

Arguments

data	input data set; see details
descol	character column name to be used for design groups

Details

The input data set must have a column with the same name as the value of descol. Other column names should be start (the time of the first observation), end (the time of the last observation), delta (the time steps to take between start and end), and add (other, ad-hoc times). Note that add might be a list-column to get a vector of times for each time grid object.

Value

The function returns a list of tgrid objects, one for each unique value found in descol.

Examples

```
idata <- tibble::tibble(ID=1:4, end=seq(24,96,24), delta=6,
add=list(c(122,124,135),c(111), c(99),c(88)))

idata <- dplyr::mutate(idata, GRP = ID %%2)

idata

l <- as_deslist(idata,"GRP")

l

lapply(l,stime)

lapply(as_deslist(idata, "ID"),stime)
```

---

blocks *Return the code blocks from a model specification file*

Description

Return the code blocks from a model specification file

Usage

```
blocks(x, ...)

## S4 method for signature 'mrgmod'
blocks(x, ...)

## S4 method for signature 'character'
blocks(x, ...)
```

Arguments

x	model object or path to model specification file
...	passed along

Examples

```
mod <- mrgsolve:::house()
mod %>% blocks
mod %>% blocks(PARAM,TABLE)
```

BLOCK_PARSE *Functions to parse code blocks*

Description

Most of the basic blocks are listed in this help topic. But see also PKMODEL which has more-involved options and is documented separately.

Usage

```
PARAM(x, env, annotated = FALSE, covariates = FALSE, pos = 1, ...)

FIXED(x, env, annotated = FALSE, pos = 1, ...)

THETA(x, env, annotated = FALSE, pos = 1, name = "THETA",
  fill = NULL, ...)

INIT(x, env, annotated = FALSE, pos = 1, ...)

CMT(x, env, annotated = FALSE, pos = 1, ...)

CAPTURE(x, env, annotated = FALSE, pos = 1, ...)
```

Arguments

x	data
env	parse environment
annotated	logical
covariates	logical
pos	block position
...	passed
name	block name
fill	data to use for block contents

See Also

PKMODEL

c,matlist-method *Operations with matlist objects*

Description

Operations with matlist objects

Usage

```
## S4 method for signature 'matlist'
c(x, ..., recursive = FALSE)
```

Arguments

x	a matlist object
...	other matlist objects
recursive	not used

c,tgrid-method *Operations with tgrid objects*

Description

Operations with tgrid objects

Usage

```
## S4 method for signature 'tgrid'
c(x, ..., recursive = FALSE)

## S4 method for signature 'tgrids'
c(x, ..., recursive = FALSE)

## S4 method for signature 'tgrid,numeric'
e1 + e2

## S4 method for signature 'tgrid,numeric'
e1 * e2

## S4 method for signature 'tgrids,numeric'
e1 + e2

## S4 method for signature 'tgrids,numeric'
e1 * e2
```

Arguments

x	mrgmod object
...	passed along to other methods
recursive	not used
e1	tgrid or tgrids object
e2	numeric value

---

carry_out *Select items to carry into simulated output*

Description

When items named in this function are found in the input data set (either data_set or idata_set), they are copied into the simulated output. Special items like evid or amt or the like are not copied from the data set per se, but they are copied from datarecord objects that are created during the simulation.

Usage

```
carry_out(x, ...)

carry.out(x, ...)
```

Arguments

x	model object
...	passed along

Details

There is also a carry.out argument to mrgsim that can be set to accomplish the same thing as a call to carry_out in the pipeline.

carry.out and carry_out. Using the underscore version is now preferred.

cmtn *Get the compartment number from a compartment name*

Description

Get the compartment number from a compartment name

Usage

```
cmtn(x, ...)

## S4 method for signature 'mrgmod'
cmtn(x, tag, ...)
```

Arguments

x	model object
...	passed along
tag	compartment name

Examples

```
mod <- mrgsolve:::house()
mod %>% cmtn("CENT")
```

code *Extract the code from a model*

Description

Extract the code from a model

Usage

```
code(x)
```

Arguments

x	an mrgsolve model object

Value

a character vector of model code

data_set *Select and modify a data set for simulation*

Description

The input data set (data_set) is a data frame that specifies observations, model events, and / or parameter values for a population of individuals.

Usage

```
data_set(x, data, ...)

## S4 method for signature 'mrgmod,data.frame'
data_set(x, data, .subset = TRUE,
  .select = TRUE, object = NULL, need = NULL, ...)

## S4 method for signature 'mrgmod,ANY'
data_set(x, data, ...)

## S4 method for signature 'mrgmod,ev'
data_set(x, data, ...)

## S4 method for signature 'mrgmod,missing'
data_set(x, object, ...)
```

Arguments

x	model object
data	data set
...	passed along
.subset	an unquoted expression passed to dplyr::filter; retain only certain rows in the data set
.select	passed to dplyr::select; retain only certain columns in the data set; this should be the result of a call to dplyr::vars()
object	character name of an object existing in $ENV to use for the data set
need	passed to inventory

Details

Input data sets are R data frames that can include columns with any valid name, however columns with selected names are treated specially by mrgsolve and incorporated into the simulation.

ID specifies the subject ID and is required for every input data set.

When columns have the same name as parameters ($PARAM in the model specification file), the values in those columns will be used to update the corresponding parameter as the simulation progresses.

Input data set may include the following columns related to PK dosing events: time, cmt, amt, rate, ii, addl, ss. Along with ID, time is a required column in the input data set unless $PRED is in use. Upper case PK dosing column names including TIME, CMT, AMT, RATE, II, ADDL, SS are also recognized. However, an error will be generated if a mix of upper case and lower case columns in this family are found.

time is the observation or event time, cmt is the compartment number (see init), amt is the dosing amount, rate is the infusion rate, ii is the dosing interval, addl specifies additional doses to administer, and ss is a flag for steady state dosing. These column names operate similarly to other non-linear mixed effects modeling software.

An error will be generated when mrgsolve detects that the data set is not sorted by time within an individual. Also, an error will be generated in case mrgsolve finds negative values for time, unless $PRED is in use.

Only numeric data can be brought in to the problem. Any non-numeric data columns will be dropped with warning. See numerics_only, which is used to prepare the data set.

An error will be generated if any parameter columns in the input data set contain NA. Likewise, and error will be generated if missing values are found in the following columns: ID, time/TIME, rate/RATE.

See exdatasets for different example data sets.

See Also

idata_set, ev, valid_data_set, valid_idata_set

Examples

```
mod <- mrgsolve:::house()

data <- expand.ev(ID=1:3, amt=c(10,20))

mod %>% data_set(data, ID > 1) %>% mrgsim

data(extran1)
head(extran1)

mod %>% data_set(extran1) %>% mrgsim
mod %>% mrgsim(data=extran1)
```

---

design *Set observation designs for the simulation*

Description

This function also allows you to assign different designs to different groups or individuals in a population.

Usage

```
design(x, deslist = list(), descol = character(0), ...)
```

Arguments

x	model object
deslist	a list of tgrid or tgrids objects or numeric vector to be used in place of ...
descol	the idata column name (character) for design assignment
...	not used

Details

This setup requires the use of an idata_set, with individual-level data passed in one ID per row. For each ID, specify a grouping variable in idata (descol). For each unique value of the grouping variable, make one tgrid object and pass them in order as ... or form them into a list and pass as deslist.

You must assign the idata_set before assigning the designs in the command chain (see the example below).

Examples

```
peak <- tgrid(0,6,0.1)
sparse <- tgrid(0,24,6)

des1 <- c(peak,sparse)
des2 <- tgrid(0,72,4)


data <- expand.ev(ID = 1:10, amt=c(100,300))
data$GRP <- data$amt/100

idata <- data[,c("ID", "amt")]

mod <- mrgsolve:::house()

mod %>%
  omat(dmat(1,1,1,1)) %>%
  carry_out(GRP) %>%
  idata_set(idata) %>%
  design(list(des1, des2),"amt") %>%
  data_set(data) %>%
  mrgsim %>%
  plot(RESP~time|GRP)
```

details *Extract model details*

Description

Extract model details

Usage

```
details(x, complete = FALSE, values = TRUE, ...)
```

Arguments

x	a model object
complete	logical; if TRUE, un-annotated parameters and compartments will be added to the output
values	logical; if TRUE, a values column will be added to the output
...	not used

Details

This function is not exported. You will have to call it with `mrgsolve:::details()`.

Examples

```
mod <- mrgsolve:::house()

mrgsolve:::details(mod)
```

env_eval *Re-evaluate the code in the ENV block*

Description

The $ENV block is a block of R code that can realize any sort of R object that might be used in running a model.

Usage

```
env_eval(x, seed = NULL)
```

Arguments

x	model object
seed	passed to set.seed if a numeric value is supplied

See Also

env_get, env_ls

`env_get` *Return model environment*

Description

Return model environment

Usage

```
env_get(x, tolist = TRUE)

env_get_env(x)
```

Arguments

x	model object
tolist	should the environment be coerced to list?

`env_ls` *List objects in the model environment*

Description

Each model keeps an internal environment that allows the user to carry any R object along. Objects are coded in $ENV.

Usage

```
env_ls(x, ...)
```

Arguments

x	model object
...	passed to ls

env_update *Update objects in model environment*

Description

Update objects in model environment

Usage

```
env_update(.x, ..., .dots = list())
```

Arguments

.x	model object
...	objects to update
.dots	list of objects to updated

ev *Event objects for simulating PK and other interventions*

Description

An event object specifies dosing or other interventions that get implemented during simulation. Event objects do similar things as data_set, but simpler and quicker.

Usage

```
ev(x, ...)

## S4 method for signature 'mrgmod'
ev(x, object = NULL, ...)

## S4 method for signature 'missing'
ev(time = 0, amt, evid = 1, cmt = 1,
  ID = numeric(0), replicate = TRUE, until = NULL, tinf = NULL,
  realize_addl = FALSE, ...)

## S4 method for signature 'ev'
ev(x, realize_addl = FALSE, ...)
```

Arguments

x	a model object
...	other items to be incorporated into the event object; see details
object	passed to show
time	event time
amt	dose amount
evid	event ID
cmt	compartment
ID	subject ID
replicate	logical; if TRUE, events will be replicated for each individual in ID
until	the expected maximum **observation** time for this regimen
tinf	infusion time; if greater than zero, then the rate item will be derived as amt/tinf
realize_addl	if FALSE (default), no change to addl doses. If TRUE, addl doses are made explicit with realize_addl

Details

- Required items in events objects include time, amt, evid and cmt.
- If not supplied, evid is assumed to be 1.
- If not supplied, cmt is assumed to be 1.
- If not supplied, time is assumed to be 0.
- If amt is not supplied, an error will be generated.
- If total is supplied, then addl will be set to total - 1.
- Other items can include ii, ss, and addl (see data_set for details on all of these items).
- ID may be specified as a vector.
- If replicate is TRUE (default), then the events regimen is replicated for each ID; otherwise, the number of event rows must match the number of IDs entered

Value

events object

See Also

ev_rep, ev_days, ev_repeat, ev_assign, ev_seq, mutate.ev, as.ev, ev_methods

Examples

```
mod <- mrgsolve:::house()

mod <- mod %>% ev(amt=1000, time=0, cmt=1)

loading <- ev(time=0, cmt=1, amt=1000)

maint <- ev(time=12, cmt=1, amt=500, ii=12, addl=10)

loading + maint
```

---

ev_assign *Replicate a list of events into a data set*

Description

Replicate a list of events into a data set

Usage

```
ev_assign(l, idata, evgroup, join = FALSE)

assign_ev(...)
```

Arguments

`l`	list of event objects
`idata`	an idata set (one ID per row)
`evgroup`	the character name of the column in `idata` that specifies event object to implement
`join`	if `TRUE`, join `idata` to the data set before returning.
`...`	used to pass arguments from `assign_ev` to `ev_assign`

Details

`ev_assign` connects events in a list passed in as the `l` argument to values in the data set identified in the `evgroup` argument. For making assignments, the unique values in the `evgroup` column are first sorted so that the first sorted unique value in `evgroup` is assigned to the first event in `l`, the second sorted value in `evgroup` column is assigned to the second event in `l`, and so on. This is a change from previous behavior, which did not sort the unique values in `evgroup` prior to making the assignments.

Examples

```
ev1 <- ev(amt=100)
ev2 <- ev(amt=300, rate=100, ii=12, addl=10)

idata <- data.frame(ID=1:10)
idata$arm <- 1+(idata$ID %%2)

ev_assign(list(ev1,ev2), idata, "arm", join=TRUE)
```

---

ev_days *Schedule dosing events on days of the week*

Description

This function lets you schedule doses on specific days of the week, allowing you to create dosing regimens on Monday/Wednesday/Friday, or Tuesday/Thursday, or every other day (however you want to define that) etc.

Usage

```
ev_days(ev = NULL, days = "", addl = 0, ii = 168,
  unit = c("hours", "days"), ...)
```

Arguments

ev	an event object
days	comma- or space-separated character string of valid days of the the week (see details)
addl	additional doses to administer
ii	inter-dose interval; intended use is to keep this at the default value
unit	time unit; the function can only currently handle hours or days
...	event objects named by one the valid days of the week (see details)

Details

Valid names of the week are:

- m for Monday
- t for Tuesday
- w for Wednesday
- th for Thursday
- f for Friday

- sa for Saturday
- s for Sunday

The whole purpose of this function is to schedule doses on specific days of the week, in a repeating weekly schedule. Please do use caution when changing ii from it's default value.

Examples

```
# Monday, Wednesday, Friday x 4 weeks
ev_days(ev(amt=100), days="m,w,f", addl=3)

# 50 mg Tuesdays, 100 mg Thursdays x 6 months
ev_days(t=ev(amt=50), th=ev(amt=100), addl=23)
```

---

ev_rep *Replicate an event object*

Description

An event sequence can be replicated a certain number of times in a certain number of IDs.

Usage

```
ev_rep(x, ID = 1, n = NULL, wait = 0, as.ev = FALSE, id = NULL)
```

Arguments

x	event object
ID	numeric vector if IDs
n	passed to ev_repeat
wait	passed to ev_repeat
as.ev	if TRUE an event object is returned
id	deprecated; use ID instead

Value

A single data.frame or event object as determined by the value of as.ev.

See Also

ev_repeat

Examples

```
e1 <- c(ev(amt=100), ev(amt=200, ii=24, addl=2, time=72))

ev_rep(e1, 1:5)
```

---

ev_repeat *Repeat a block of dosing events*

Description

Repeat a block of dosing events

Usage

```
ev_repeat(x, n, wait = 0, as.ev = FALSE)
```

Arguments

x	event object or dosing data frame
n	number of times to repeat
wait	time to wait between repeats
as.ev	if TRUE, an event object is returned; otherwise a data.frame is returned

Value

See as.ev argument.

---

ev_rx *Create intervention objects from Rx input*

Description

See details below for Rx specification. Actual parsing is done by parse_rx; this function can be used to debug Rx inputs.

Usage

```
ev_rx(x, y, ...)

## S4 method for signature 'mrgmod,character'
ev_rx(x, y, ...)

## S4 method for signature 'character,missing'
ev_rx(x, df = FALSE, ...)

parse_rx(x)
```

Arguments

x	a model object or character Rx input
y	character Rx input; see details
...	not used at this time
df	if TRUE then a data frame is returned

Value

The method dispatched on model object (mrgmod) returns another model object. The character method returns an event object. The parse_rx function return a list named with arguments for the event object constructor ev.

Rx specification

- The dose is found at the start of the string by sequential digits; this may be integer, decimal, or in scientific notation
- Use in to identify the dosing compartment number; must be integer
- Use q to identify the dosing interval; must be integer or decimal number (but not scientific notation)
- Use over to indicate an infusion and its duration; integer or decimal number
- Use x to indicate total number of doses; must be integer
- Use then or , to separate dosing periods
- User after to insert a lag in the start of a period; integer or decimal number (but not scientific notation)

Examples

```
# example("ev_rx")

ev_rx("100")

ev_rx("100 in 2")

ev_rx("100 q12 x 3")

ev_rx("100 over 2")

ev_rx("100 q 24 x 3 then 50 q12 x 2")

ev_rx("100 then 50 q 24 after 12")

ev_rx("100.2E-2 q4")

ev_rx("100 over 2.23")

ev_rx("100 q 12 x 3")

parse_rx("100 mg q 24 then 200 mg q12")
```

ev_seq *Schedule a series of event objects*

Description

Schedule a series of event objects

Usage

```
ev_seq(..., ID = NULL, .dots = NULL, id = NULL)

## S3 method for class 'ev'
seq(...)
```

Arguments

...	event objects or numeric arguments named wait
ID	numeric vector of subject IDs
.dots	a list of event objects that replaces ...
id	deprecated; use ID

Details

The doses for the next event line start after all of the doses from the previous event line plus one dosing interval from the previous event line (see examples).

When numerics named wait are mixed in with the event objects, a period with no dosing activity is incorporated into the sequence, between the adjacent dosing event objects. Values for wait can be negative.

Values for time in any event object act like a prefix time spacer wherever that event occurs in the event sequence (see examples).

Use the generic seq when the first argument is an event object. If a waiting period is the first event, you will need to use ev_seq. When an event object has multiple rows, the end time for that sequence is taken to be one dosing interval after the event that takes place on the last row of the event object.

Value

A single event object.

Examples

```
e1 <- ev(amt=100, ii=12, addl=1)

e2 <- ev(amt=200)

seq(e1, e2)
```

```
seq(e1, wait = 8, e2)

seq(e1, wait = 8, e2, ID = 1:10)

ev_seq(wait = 12, e1, wait = 120, e2, wait = 120, e1)

seq(ev(amt=100, ii=12), ev(time=8, amt=200))
```

`exdatasets` *Example input data sets*

Description

Example input data sets

Usage

```
data(exidata)

data(extran1)

data(extran2)

data(extran3)

data(exTheoph)

data(exBoot)
```

Details

- `exidata` holds individual-level parameters and other data items, one per row
- `extran1` is a "condensed" data set
- `extran2` is a full dataset
- `extran3` is a full dataset with parameters
- `exTheoph` is the theophylline data set, ready for input into `mrgsolve`
- `exBoot` a set of bootstrap parameter estimates

Examples

```
mod <- mrgsolve:::house() %>% update(end=240) %>% Req(CP)

## Full data set
data(exTheoph)
```

```
out <- mod %>% data_set(exTheoph) %>% mrgsim
out
plot(out)

## Condensed: mrgsolve fills in the observations
data(extran1)
out <- mod %>% data_set(extran1) %>% mrgsim
out
plot(out)

## Add a parameter to the data set
stopifnot(require(dplyr))
data <- extran1 %>% distinct(ID) %>% select(ID) %>%
  mutate(CL=exp(log(1.5) + rnorm(nrow(.), 0,sqrt(0.1)))) %>%
  left_join(extran1,.)

data

out <- mod %>% data_set(data) %>% carry.out(CL) %>%  mrgsim
out
plot(out)

## idata
data(exidata)
out <- mod %>% idata_set(exidata) %>% ev(amt=100,ii=24,addl=10) %>% mrgsim
plot(out, CP~time|ID)
```

`expand.idata` *Create template data sets for simulation*

Description

Create template data sets for simulation

Usage

```
expand.idata(...)

expand.ev(...)
```

Arguments

`...`	passed to expand.grid

Details

An ID column is added as `seq(nrow(ans))` if not supplied by the user. For `expand.ev`, defaults also added include `cmt = 1`, `time = 0`, `evid = 1`. If `total` is included, then `addl` is derived as `total` - 1. If `tinf` is included, then an infusion rate is derived for row where `tinf` is greater than zero.

Examples

```
idata <- expand.idata(CL = c(1,2,3), VC = c(10,20,30))

doses <- expand.ev(amt = c(300,100), ii = c(12,24), cmt = 1)

infusion <- expand.ev(amt = 100, tinf = 2)
```

---

expand_observations *Insert observations into a data set*

Description

Insert observations into a data set

Usage

```
expand_observations(data, times, unique = FALSE)
```

Arguments

data	a data set or event object
times	a vector of observation times
unique	'logical'; if 'TRUE' then values for 'time' are dropped if they are found anywhere in 'data'

Details

Non-numeric columns will be dropped with a warning.

Value

A data frame

Examples

```
data <- expand.ev(amt = c(100,200,300))

expand_observations(data, times = seq(0,48,2))
```

house *Return a pre-compiled, PK/PD model*

Description

Return a pre-compiled, PK/PD model

Usage

```
house(...)
```

Arguments

...	passed to update

Value

A packmod object, ready to simulate.

Examples

```
mod <- mrgsolve:::house()

see(mod)

mod %>% ev(amt=100) %>% mrgsim %>% plot
```

idata_set *Select and modify a idata set for simulation*

Description

The individual data set (idata_set) is a data frame with one row for each individual in a population, specifying parameters and other individual-level data.

Usage

```
idata_set(x, data, ...)

## S4 method for signature 'mrgmod,data.frame'
idata_set(x, data, .subset = TRUE,
  .select = TRUE, object = NULL, need = NULL, ...)

## S4 method for signature 'mrgmod,ANY'
```

```
idata_set(x, data, ...)

## S4 method for signature 'mrgmod,missing'
idata_set(x, object, ...)
```

Arguments

x	model object
data	a data set that can be coerced to data.frame
...	passed along
.subset	an unquoted expression passed to dplyr::filter; retain only certain rows in the data set
.select	passed to dplyr::select; retain only certain columns in the data set; this should be the result of a call to dplyr::vars()
object	character name of an object existing in $ENV to use for the data set
need	passed to inventory

Details

The idata_set is a data.frame that specifies individual-level data for the problem. An ID column is required and there can be no more than one row in the data frame for each individual.

In most cases, the columns in the idata_set have the same names as parameters in the param list. When this is the case, the parameter set is updated as the simulation proceeds once at the start of each individual. The 'idata_set' can also be used to set initial conditions for each individual: for a compartment called CMT, make a column in idata_set called CMT_0 and make the value the desired initial value for that compartment. Note that this initial condition will be over-ridden if you also set the CMT_0 in $MAIN.

The most common application of idata_set is to specify a population or batch of simulations to do. We commonly use idata_set with an event object (see ev). In that case, the event gets applied to each individual in the idata_set.

It is also possible to provide both a data_set and a idata_set. In this case, the idata_set is used as a parameter lookup for IDs found in the data_set. Remember in this case, it is the data_set (not the idata_set) that determines the number of individuals in the simulation.

An error will be generated if any parameter columns in the input idata set contain NA.

See Also

data_set, ev

Examples

```
mod <- mrgsolve:::house()

data(exidata)

exidata
```

```
mod %>%
  idata_set(exidata, ID <= 2) %>%
  ev(amt = 100) %>%
  mrgsim() %>%
  plot()

mod %>%
  idata_set(exidata) %>%
  ev(amt = 100) %>%
  mrgsim()

mod %>% ev(amt = 100) %>% mrgsim(idata=exidata)
```

`init` *Methods for working with the model compartment list*

Description

Calling `init` with the model object as the first argument will return the model initial conditions as a `numericlist` object. See `numericlist` for methods to deal with `cmt_list` objects.

Usage

```
init(.x, ...)

## S4 method for signature 'mrgmod'
init(.x, .y = list(), ..., .pat = "*")

## S4 method for signature 'mrgsims'
init(.x, ...)

## S4 method for signature 'missing'
init(.x, ...)

## S4 method for signature 'list'
init(.x, ...)

## S4 method for signature 'ANY'
init(.x, ...)
```

Arguments

`.x`	the model object
`...`	passed along
`.y`	list to be merged into parameter list
`.pat`	a regular expression (character) to be applied as a filter when printing compartments to the screen

Details

Can be used to either get a compartment list object from a mrgmod model object or to update the compartment initial conditions in a model object. For both uses, the return value is a cmt_list object. For the former use, init is usually called to print the compartment initial conditions to the screen, but the cmt_list object can also be coerced to a list or numeric R object.

Value

an object of class cmt_list (see numericlist)

Examples

```
## example("init")
mod <- mrgsolve:::house()

init(mod)
init(mod, .pat="^C") ## may be useful for large models

class(init(mod))

init(mod)$CENT

as.list(init(mod))
as.data.frame(init(mod))
```

---

inventory *Check whether all required parameters needed in a model are present in an object*

Description

Check whether all required parameters needed in a model are present in an object

Usage

```
inventory(x, obj, ..., .strict = FALSE)
```

Arguments

x	model object
obj	data.frame to pass to idata_set or data_set
...	capture dplyr-style parameter requirements
.strict	whether to stop execution if all requirements are present (TRUE) or just warn (FALSE); see details

Details

If parameter requirements are not explicitly stated, the requirement defaults to all parameter names in x. Note that, by default, the inventory is not .strict unless the user explicitly states the parameter requirement. That is, if parameter requirements are explicitly stated, .strict will be set to TRUE if a value .strict was not passed in the call.

Value

original mrgmod

Examples

```
## Not run:
inventory(mod, idata, CL:V) # parameters defined, inclusively, CL through Volume
inventory(mod, idata, everything()) # all parameters
inventory(mod, idata, contains("OCC")) # all parameters containing OCC
inventory(mod, idata, -F) # all parameters except F

## End(Not run)
```

---

is.mrgmod *Check if an object is a model object*

Description

The function checks to see if the object is either mrgmod or packmod.

Usage

```
is.mrgmod(x)
```

Arguments

x	any object

Value

TRUE if x inherits mrgsims.

is.mrgsims *Check if an object is mrgsim output*

Description

Check if an object is mrgsim output

Usage

```
is.mrgsims(x)
```

Arguments

x	any object

Value

TRUE if x inherits mrgsims.

lctran *Convert select upper case column names to lower case to conform to mrgsolve data expectations*

Description

Convert select upper case column names to lower case to conform to mrgsolve data expectations

Usage

```
lctran(data)
```

Arguments

data	an nmtran-like data frame

Details

Columns that will be renamed with lower case versions: AMT, II, SS, CMT, ADDL, RATE, EVID, TIME. If a lower case version of these names exist in the data set, the column will not be renamed.

Value

A data.frame with renamed columns

`loadso` *Load the model shared object*

Description

Once the model is compiled, the model object can be used to re-load the model shared object (the compiled code underlying the mode) when the simulation is to be done in a different R process.

Usage

```
loadso(x, ...)

## S3 method for class 'mrgmod'
loadso(x, ...)
```

Arguments

`x`	the model object
`...`	not used

Details

The ‘loadso‘ function most frequently needs to be used when parallelizing simulations across worker nodes. The model can be run after calling ‘loadso‘, without requiring that it is re-compiled on worker nodes. It is likely required that the model is built (and the shared object stored) in a local directory off of the working R directory (see the second example).

Value

The model object (invisibly).

Examples

```
## Not run:
  mod <- mread("pk1", modlib())
  loadso(mod)

  mod2 <- mread("pk2", modlib(), soloc = "build")
  loadso(mod2)

## End(Not run)
```

`matrix_helpers` *Create matrices from vector input*

Description

Create matrices from vector input

Usage

```
bmat(..., correlation = FALSE, digits = -1)

cmat(..., digits = -1)

dmat(...)
```

Arguments

`...`	matrix data
`correlation`	logical; if TRUE, off diagonal elements are assumed to be correlations and converted to covariances
`digits`	if greater than zero, matrix is passed to signif (along with digits) prior to returning

Details

`bmat` makes a block matrix. `cmat` makes a correlation matrix. `dmat` makes a diagonal matrix.

See Also

`as_bmat`

`as_dmat`

Examples

```
dmat(1,2,3)/10

bmat(0.5,0.01,0.2)

cmat(0.5, 0.87,0.2)
```

mcode *Write, compile, and load model code*

Description

This is a convenience function that ultimately calls mread. Model code is written to a file and read back in using mread.

Usage

```
mcode(model, code, project = getOption("mrgsolve.project", tempdir()),
  ...)

mcode_cache(model, code, project = getOption("mrgsolve.project",
  tempdir()), ...)
```

Arguments

model	model name
code	character string specifying a mrgsolve model
project	project name
...	passed to mread; see that help topic for other arguments that can be set

Details

Note that the arguments are in slightly different order than mread. The default project is tempdir().

See the mread help topic for discussion about caching compilation results with mcode_cache.

See Also

mread, mread_cache

Examples

```
## Not run:
code <- '
$CMT DEPOT CENT
$PKMODEL ncmt=1, depot=TRUE
$MAIN
double CL = 1;
double V = 20;
double KA = 1;
'

mod <- mcode("example",code)

## End(Not run)
```

mcRNG *Set RNG to use L'Ecuyer-CMRG*

Description

Set RNG to use L'Ecuyer-CMRG

Usage

```
mcRNG()
```

modlib *Internal model library*

Description

Internal model library

Usage

```
modlib(model = NULL, ..., list = FALSE)
```

Arguments

model	character name of a model in the library
...	passed to mread_cache
list	list available models

Details

See modlib_details, modlib_pk, modlib_pkpd, modlib_tmdd, modlib_viral for details.

Call modlib("<modelname>") to compile and load a mode from the library.

Call modlib(list=TRUE) to list available models. Once the model is loaded (see examples below), call as.list(mod)$code to see model code and equations.

Examples

```
## Not run:
mod <- mread("pk1cmt", modlib())
mod <- mread("pk2cmt", modlib())
mod <- mread("pk3cmt", modlib())
mod <- mread("pk1",    modlib())
mod <- mread("pk2",    modlib())
mod <- mread("popex",  modlib())
mod <- mread("irm1",   modlib())
```

```
mod <- mread("irm2",   modlib())
mod <- mread("irm3",   modlib())
mod <- mread("irm4",   modlib())
mod <- mread("emax",   modlib())
mod <- mread("effect", modlib())
mod <- mread("tmdd",   modlib())
mod <- mread("viral1", modlib())
mod <- mread("viral2", modlib())
mod <- mread("pred1",  modlib())
mod <- mread("pbpk",   modlib())

mrgsolve:::code(mod)

## End(Not run)
```

`modlib_details` *modlib: PK/PD Model parameters, compartments, and output variables*

Description

modlib: PK/PD Model parameters, compartments, and output variables

Compartments

- `EV1`, `EV2`: extravascular dosing compartments
- `CENT`: central PK compartment
- `PERIPH`: peripheral PK compartment
- `PERIPH2`: peripheral PK compartment 2
- `RESP`: response PD compartment (irm models)

Output variables

- `CP`: concentration in the central compartment (`CENT/VC`)
- `RESP`: response (emax model)

PK parameters

- `KA1`, `KA2`: first order absorption rate constants from first and second extravascular compartment (1/time)
- `CL`: clearance (volume/time)
- `VC`: volume of distribution, central compartment (volume)
- `VP`: volume of distribution, peripheral compartment (volume)
- `VP2`: volume of distribution, peripheral compartment 2 (volume)
- `Q`: intercompartmental clearance (volume/time)

- Q2: intercompartmental clearance 2 (volume/time)
- VMAX: maximum rate, nonlinear process (mass/time)
- KM: Michaelis constant (mass/volume)
- K10: elimination rate constant (1/time); CL/VC
- K12: rate constant for transfer to peripheral compartment from central (1/time); Q/VC
- K21: rate constant for transfer to central compartment from peripheral (1/time); Q/VP

PD parameters

- E0: baseline effect (emax model)
- EMAX, IMAX: maximum effect (response)
- EC50, IC50: concentration producing 50 percent of effect (mass/volume)
- KIN: zero-order response production rate (irm models) (response/time)
- KOUT: first-order response elimination rate (irm models) (1/time)
- n: sigmoidicity factor
- KEO: rate constant for transfer to effect compartment (1/time)

---

modlib_pk *modlib: Pharmacokinetic models*

Description

modlib: Pharmacokinetic models

Arguments

...	passed to update

Details

See modlib_details for more detailed descriptions of parameters and compartments.

The pk1cmt model is parameterized in terms of CL, VC, KA1 and KA2 and uses compartments EV1, EV2, and CENT. The pk2cmt model adds a PERIPH compartment and parameters Q and VP to that of the one-compartment model. Likewise, the three-compartment model (pk3cmt) adds PERIPH2 and parameters Q2 and VP2 to that of the two-compartment models. All pk models also have parameters VMAX (defaulting to zero, no non-linear clearance) and KM.

Value

an object of class packmod

Model description

All pk models have two extravascular dosing compartments and potential for linear and nonlinear clearance.

- pk1cmt: one compartment pk model using ODEs
- pk2cmt: two compartment pk model using ODEs
- pk3cmt: three compartment pk model using ODEs
- pk1: one compartment pk model in closed-form
- pk2: two compartment pk model in closed-form
- popex: a simple population pk model

---

modlib_pkpd *modlib: Pharmacokinetic / pharmacodynamic models*

Description

modlib: Pharmacokinetic / pharmacodynamic models

Details

See modlib_details for more detailed descriptions of parameters and compartments.

All PK/PD models include 2-compartment PK model with absorption from 2 extravascular compartments and linear + nonlinear clearance. The PK models are parameterized with CL, VC, Q, VMAX, KM, KA1 and KA2 and implement compartments EV1, EV2, CENT, PERIPH . The indirect response models have compartment RESP and the emax model has output variable RESP. PD parameters include KIN, KOUT, IC50, EC50, IMAX, EMAX, E0, and n.

Also, once the model is loaded, use see method for mrgmod to view the model code.

Model description

- irm1 inhibition of response production
- irm2 inhibition of response loss
- irm3 stimulation of response production
- irm4 stimulation of response loss
- pd_effect effect compartment model
- emax sigmoid emax model

`modlib_tmdd` *modlib: Target mediated disposition model*

Description

modlib: Target mediated disposition model

Arguments

...	passed to update

Parameters

- `KEL`: elimination rate constant
- `KTP`: tissue to plasma rate constant
- `KPT`: plasma to tissue rate constant
- `VC`: volume of distribution
- `KA1`, `KA2`: absorption rate constants
- `KINT`: internalization rate constant
- `KON`: association rate constant
- `KOFF`: dissociation rate constant
- `KSYN`: target synthesis rate
- `KDEG`: target degredation rate constant

Compartments

- `CENT`: unbound drug in central compartment
- `TISS`: unbound drug in tissue compartment
- `REC`: concentration of target
- `RC`: concentration of drug-target complex
- `EV1`, `EV2`: extravascular dosing compartments

Output variables

- `CP`: unbound drug in the central compartment
- `TOTAL`: total concentration of target (complexed and uncomplexed)

`modlib_viral` *modlib: HCV viral dynamics models*

Description

modlib: HCV viral dynamics models

Models

- `viral1`: viral dynamics model with single HCV species
- `viral2`: viral dynamics model with wild-type and mutant HCV species

Parameters

- `s`: new hepatocyte synthesis rate (cells/ml/day)
- `d`: hepatocyte death rate constant (1/day)
- `p`: viral production rate constant (copies/cell/day)
- `beta`: new infection rate constant (ml/copy/day)
- `delta`: infected cell death rate constant (1/day)
- `c`: viral clearance rate constant (1/day)
- `fit`: mutant virus fitness
- `N`: non-target hepatocytes
- `mu`: forward mutation rate
- `Tmax`: maximum number of target hepatocytes (cells/ml)
- `rho`: maximum hepatocyte regeneration rate (1/day)

Compartments

- `T`: uninfected target hepatocytes (cells/ml)
- `I`: productively infected hepatocytes (cells/ml)
- `V`: hepatitis C virus (copies/ml)
- `IM`: mutant infected hepatocytes (cells/ml)
- `VM`: mutant hepatitis C virus (copies/ml)
- `expos`: exposure metric to drive pharmacodynamic model

mread *Read a model specification file*

Description

mread reads and parses the mrgsolve model specification file, builds the model, and returns a model object for simulation. mread_cache does the same, but caches the compilation result for later use.

Usage

```
mread(model, project = getOption("mrgsolve.project", getwd()),
  code = NULL, file = NULL, udll = TRUE, ignore.stdout = TRUE,
  raw = FALSE, compile = TRUE, audit = TRUE,
  quiet = getOption("mrgsolve_mread_quiet", FALSE),
  check.bounds = FALSE, warn = TRUE,
  soloc = getOption("mrgsolve.soloc", tempdir()), preclean = FALSE,
  ...)

mread_cache(model = NULL, project = getOption("mrgsolve.project",
  getwd()), file = paste0(model, ".cpp"), code = NULL,
  soloc = getOption("mrgsolve.soloc", tempdir()), quiet = FALSE,
  preclean = FALSE, ...)

mread_file(file, ...)
```

Arguments

model	model name
project	location of the model specification file an any headers to be included; see also the discussion about model; this argument can be set via options() library under details as well as the modlib help topic
code	a character string with model specification code to be used instead of a model file
file	the full file name (with extension, but without path) where the model is specified
udll	use unique name for shared object
ignore.stdout	passed to system call for compiling model
raw	if TRUE, return a list of raw output
compile	logical; if TRUE, the model will be built
audit	check the model specification file for errors
quiet	don't print messages when compiling
check.bounds	check boundaries of parameter list
warn	logical; if TRUE, print warning messages that may arise

soloc	the directory location where the model shared object is built and stored; see details; this argument can be set via options(); if the directory does not exist, 'mread' will attempt to create it.
preclean	logical; if TRUE, compilation artifacts are cleaned up first
...	passed to update

Details

The model argument is required. For typical use, the file argument is omitted and the value for file is generated from the value for model. To determine the source file name, mrgsolve will look for a file extension in model. A file extension is assumed when it finds a period followed by one to three alpha-numeric characters at the end of the string (e.g. mymodel.txt but not my.model). If no file extension is found, the extension .cpp is assumed (e.g. file is <model-name>.cpp). If a file extension is found, file is <model-name>.

Best practice is to avoid using . in model unless you are using model to point to the model specification file name. Otherwise, use mread_file.

Use the soloc argument to specify a directory location for building the model. This is the location where the model shared object will be stored on disk. The default is a temporary directory, so compilation artifacts are lost when R restarts when the default is used. Changing soloc to a persistent directory location will preserve those artifacts across R restarts. Also, if simulation from a single model is being done in separate processes on separate compute nodes, it might be necessary to store these compilation artifacts in a local directory to make them accessible to the different nodes. If the soloc directory does not exist, 'mread' will attempt to create it.

Similarly, using mread_cache will cache results in the temporary directory and the cache cannot be accessed after the R process is restarted.

Model Library

mrgsolve comes bundled with several precoded PK, PK/PD, and other systems models that are accessible via the mread interface.

Models available in the library include:

- PK models: pk1cmt, pk2cmt, pk3cmt, pk1, pk2, popex, tmdd
- PKPD models: irm1, irm2, irm3, irm4, emax, effect
- Other models: viral1, viral2

When the library model is accessed, mrgsolve will compile and load the model as you would for any other model. It is only necessary to reference the correct model name and point the project argument to the mrgsolve model library location via modlib.

For more details, see modlib_pk, modlib_pkpd, modlib_tmdd, modlib_viral, and modlib_details for more information about the state variables and parameters in each model.

See Also

mcode, mcode_cache

Examples

```
## Not run:
code <- '
$PARAM CL = 1, VC = 5
$CMT CENT
$ODE dxdt_CENT = -(CL/VC)*CENT;
'

mod <- mcode("ex_mread", code)

mod

mod %>% init(CENT=1000) %>% mrgsim %>% plot


mod <- mread("irm3", modlib())

mod

# if the model is in the file mymodel.cpp
mod <- mread("mymodel")

# if the model is in the file mymodel.txt
mod <- mread(file = "mymodel.txt")

or

mod <- mread_file("mymodel.txt")



## End(Not run)
```

`mrgsim` *Simulate from a model object*

Description

This function sets up the simulation run from data stored in the model object as well as arguments passed in. Use `mrgsim_q` instead to benchmark mrgsolve or to do repeated quick simulation for tasks like parameter optimization, sensitivity analyses, or optimal design. See `mrgsim_variants` for other mrgsim-like functions that have more focused inputs. `mrgsim_df` coerces output to data.frame prior to returning.

Usage

```
mrgsim(x, data = NULL, idata = NULL, events = NULL, nid = 1, ...)
```

```
mrgsim_df(..., output = "df")

do_mrgsim(x, data, idata = no_idata_set(), carry_out = carry.out,
  carry.out = character(0), seed = as.integer(NA),
  Request = character(0), output = NULL, capture = NULL,
  obsonly = FALSE, obsaug = FALSE, tgrid = NULL, recsort = 1,
  deslist = list(), descol = character(0), filbak = TRUE,
  tad = FALSE, nocb = TRUE, skip_init_calc = FALSE, ...)
```

Arguments

x	the model object
data	NMTRAN-like data set (see data_set)
idata	a matrix or data frame of model parameters, one parameter per row (see idata_set)
events	an event object
nid	integer number of individuals to simulate; only used if idata and data are missing
...	passed to update and do_mrgsim
output	if NULL (the default) a mrgsims object is returned; otherwise, pass df to return a data.frame or matrix to return a matrix
carry_out	data items to copy into the output
carry.out	soon to be deprecated; use carry_out instead
seed	deprecated
Request	compartments or captured variables to retain in the simulated output; this is different than the request slot in the model object, which refers only to model compartments
capture	character file name used for debugging (not related to $CAPTURE)
obsonly	if TRUE, dosing records are not included in the output
obsaug	augment the data set with time grid observations; when TRUE and a full data set is used, the simulated output is augmented with an observation at each time in stime(). When using obsaug, a flag indicating augmented observations can be requested by including a.u.g in carry_out
tgrid	a tgrid object; or a numeric vector of simulation times or another object with an stime method
recsort	record sorting flag. Default value is 1. Possible values are 1,2,3,4: 1 and 2 put doses in a data set after padded observations at the same time; 3 and 4 put those doses before padded observations at the same time. 2 and 4 will put doses scheduled through addl after observations at the same time; 1 and 3 put doses scheduled through addl before observations at the same time. recsort will not change the order of your input data set if both doses and observations are given.
deslist	a list of tgrid objects
descol	the name of a column for assigning designs
filbak	carry data items backward when the first data set row has time greater than zero

tad	when TRUE a column is added to simulated output is added showing the time since the last dose. Only data records with evid == 1 will be considered doses for the purposes of tad calculation. The tad can be properly calculated with a dosing lag time in the model as long as the dosing lag time (specified in $MAIN) is always appropriate for any subsequent doses scheduled through addl. This will always be true if the lag time doesn't change over time. But it might (possibly) not hold if the lag time changes prior to the last dose in the addl sequence. This known limitation shouldn't affect tad calculation in most common dosing lag time implementations.
nocb	if TRUE, use next observation carry backward method; otherwise, use locf.
skip_init_calc	don't use $MAIN to calculate initial conditions

Details

- Use mrgsim_df to return a data frame rather than mrgsims object.
- Both data and idata will be coerced to numeric matrix
- carry_out can be used to insert data columns into the output data set. This is partially dependent on the nature of the data brought into the problem.
- When using data and idata together, an error is generated if an ID occurs in data but not idata. Also, when looking up data in idata, ID in idata is assumed to be uniquely keyed to ID in data. No error is generated if ID is duplicated in data; parameters will be used from the first occurrence found in idata.
- carry_out: idata is assumed to be individual-level and variables that are carried from idata are repeated throughout the individual's simulated data. Variables carried from data are carried via last-observation carry forward. NA is returned from observations that are inserted into simulated output that occur prior to the first record in data.

Value

An object of class mrgsims

See Also

mrgsim_variants, mrgsim_q

Examples

```
## example("mrgsim")

e <- ev(amt = 1000)

mod <- mrgsolve:::house()

out <- mod %>% ev(e) %>% mrgsim()

plot(out)

out <- mod %>% ev(e) %>% mrgsim(end=22)
```

```
out

data(exTheoph)

out <- mod %>% data_set(exTheoph) %>% mrgsim()

out

out <- mod %>% mrgsim(data=exTheoph)

out <- mrgsim(mod, data=exTheoph, obsonly=TRUE)

out

out <- mod %>% mrgsim(data=exTheoph, obsaug=TRUE, carry_out="a.u.g")

out

out <- mod %>% ev(e) %>% mrgsim(req="CENT")

out

out <- mrgsim(mod, Req="CP,RESP", events = e)

out
```

`mrgsims_dplyr` *Methods for handling output with dplyr verbs*

Description

Methods for handling output with dplyr verbs

Usage

```
## S3 method for class 'mrgsims'
as.tbl(x, ...)

## S3 method for class 'mrgsims'
pull(.data, ...)

## S3 method for class 'mrgsims'
filter_(.data, ...)

filter_sims(.data, ...)

## S3 method for class 'mrgsims'
```

```
group_by(.data, ..., add = FALSE)

## S3 method for class 'mrgsims'
distinct(.data, ..., .keep_all = FALSE)

## S3 method for class 'mrgsims'
mutate(.data, ...)

mutate_sims(.data, ...)

## S3 method for class 'each'
summarise(.data, funs, ...)

## S3 method for class 'mrgsims'
summarise(.data, ...)

## S3 method for class 'mrgsims'
do(.data, ..., .dots)

## S3 method for class 'mrgsims'
select(.data, ...)

## S3 method for class 'mrgsims'
slice(.data, ...)

as_data_frame.mrgsims(.data_, ...)

## S3 method for class 'mrgsims'
as_tibble(.data_, ...)
```

Arguments

x	mrgsims object
...	passed to other methods
.data	passed to various dplyr functions
add	passed to dplyr::group_by
.keep_all	passed to dplyr::distinct
funs	passed to dplyr::summarise_each
.dots	passed to various dplyr functions
.data_	mrgsims object

mrgsim_q *Simulate from a model object with quicker turnaround*

Description

Use the function when you would usually use mrgsim_d, but you need a quicker turnaround time. The timing differences might be difficult to detect for a single simulation run but could become appreciable with repeated simulation. See details for important differences in how mrgsim_q is invoked compared to mrgsim and mrgsim_d. This function should always be used for benchmarking simulation time with mrgsolve.

Usage

```
mrgsim_q(x, data, recsort = 1, stime = numeric(0), output = NULL,
  skip_init_calc = FALSE)
```

Arguments

x	a model object
data	a simulation data set
recsort	record sorting flag
stime	a numeric vector of observation times; these observation times will only be added to the output if there are no observation records in data
output	output data type; if NULL, then an mrgsims object is returned; if "df" then a data frame is returned
skip_init_calc	don't use $MAIN to calculate initial conditions

Details

This function does not support the piped simulation workflow. All arguments must be passed into the function except for x.

A data set is required for this simulation workflow. The data set can have only dosing records or doses with observations. When the data set only includes doses, a single numeric vector of observation times should be passed in.

This simulation workflow does not support Req (request) functionality. All compartments and captured variables will always be returned in the simulation output.

This simulation workflow does not support carry-out functionality.

This simulation workflow does not accept arguments to be passed to update. This must be done by a separate call to update.

This simulation workflow does not support use of event objects. If an event object is needed, it should be converted to a data set prior to the simulation run (see as_data_set or as.data.frame.ev.

This simulation workflow does not support idata sets or any feature enabled by idata set use. Individual level parameters should be joined onto the data set prior to simulation. Otherwise mrgsim_i or mrgsim_ei should be used.

By default, a mrgsims object is returned (as with mrgsim). Use the matrix_return argument to request a plain matrix of simulated data on return.

See Also

mrgsim, mrgsim_variants

Examples

```
mod <- mrgsolve:::house()

data <- expand.ev(amt = c(100,300,1000))

out <- mrgsim_q(mod,data)

out
```

---

mrgsim_variants *mrgsim variant functions*

Description

These functions are called by mrgsim and have explicit input requirements written into the function name. The motivation behind these variants is to give the user a clear workflow with specific, required inputs as indicated by the function name. Use mrgsim_q instead to benchmark mrgsolve or to do repeated quick simulation for tasks like parameter optimization, sensitivity analyses, or optimal design.

Usage

```
mrgsim_e(x, events, idata = NULL, data = NULL, ...)

mrgsim_d(x, data, idata = NULL, events = NULL, ...)

mrgsim_ei(x, events, idata, data = NULL, ...)

mrgsim_di(x, data, idata, events = NULL, ...)

mrgsim_i(x, idata, data = NULL, events = NULL, ...)

mrgsim_0(x, idata = NULL, data = NULL, events = NULL, ...)
```

Arguments

x	the model object
events	an event object
idata	a matrix or data frame of model parameters, one parameter per row (see idata_set)
data	NMTRAN-like data set (see data_set)
...	passed to update and do_mrgsim

Details

Important: all of these functions require that data, idata, and/or events be pass directly to the functions. They will not recognize these inputs from a pipeline.

- mrgsim_e simulate using an event object
- mrgsim_ei simulate using an event object and idata_set
- mrgsim_d simulate using a data_set
- mrgsim_di simulate using a data_set and idata_set
- mrgsim_i simulate using a idata_set
- mrgsim_0 simulate using just the model
- mrgsim_q simulate from a data set with quicker turnaround (see mrgsim_q)

See Also

mrgsim, mrgsim_q

---

mrgsolve *mrgsolve*

Description

mrgsolve is an R package maintained under the auspices of Metrum Research Group that facilitates simulation from models based on systems of ordinary differential equations (ODE) that are typically employed for understanding pharmacokinetics, pharmacodynamics, and systems biology and pharmacology. mrgsolve consists of computer code written in the R and C++ languages, providing an interface to the DLSODA differential equation solver (written in FORTRAN) provided through ODEPACK - A Systematized Collection of ODE Solvers.

Resources

- Main mrgsolve resource page: https://mrgsolve.github.io
- User guide: https://mrgsolve.github.io/user_guide
- Vignettes: https://mrgsolve/github.io/vignettes

Also see

- Package index, including a listing of all functions

Examples

```
## example("mrgsolve")

mod <- mrgsolve:::house(delta=0.1)  %>% param(CL=0.5)

events <-  ev(amt=1000, cmt=1, addl=5, ii=24)

events

mod

see(mod)

stime(mod)

param(mod)
init(mod)

out <- mod %>% ev(events) %>% mrgsim(end=168)

out

head(out)
tail(out)
dim(out)

plot(out, GUT+CP~.)

sims <- as.data.frame(out)

t72 <- dplyr::filter(sims, time==72)
str(t72)

idata <- data.frame(ID=c(1,2,3), CL=c(0.5,1,2),VC=12)
out <- mod %>% ev(events) %>% mrgsim(end=168, idata=idata, req="")
plot(out)

out <- mod %>% ev(events) %>% mrgsim(carry.out="amt,evid,cmt,CL")
head(out)

out <-
  mod %>%
  ev() %>%
  knobs(CL=c(0.5, 1,2), amt=c(100,300,1000), cmt=1,end=48)

plot(out, CP~., scales="same")
plot(out, RESP+CP~time|amt,groups=CL)
```

```
ev1 <- ev(amt=500, cmt=2,rate=10)
ev2 <- ev(amt=100, cmt=1, time=54, ii=8, addl=10)
events <- ev1+ev2
events

out <- mod %>% ev(ev1+ev2) %>% mrgsim(end=180, req="")
plot(out)



## "Condensed" data set
data(extran1)
extran1

out <- mod %>% data_set(extran1) %>% mrgsim(end=200)

plot(out,CP~time|factor(ID))


## idata
data(exidata)
exidata

out <-
  mod %>%
  ev(amt=1000, cmt=1) %>%
  idata_set(exidata) %>%
  mrgsim(end=72)

plot(out, CP~., as="log10")


# Internal model library
## Not run:
mod <- mread("irm1", modlib())

mod

mod %>% ev(amt=300, ii=12, addl=3) %>% mrgsim


## End(Not run)
```

`mutate.ev` *dplyr verbs for event objects*

Description

dplyr verbs for event objects

Usage

```
## S3 method for class 'ev'
mutate(.data, ...)

## S3 method for class 'ev'
select(.data, ...)

## S3 method for class 'ev'
filter_(.data, ...)
```

Arguments

.data	the event object
...	passed to the dplyr function

---

names,mrgmod-method *Get all names from a model object*

Description

Get all names from a model object

Usage

```
## S4 method for signature 'mrgmod'
names(x)
```

Arguments

x	the model object

Examples

```
mod <- mrgsolve:::house()
names(mod)
```

nmxml *Get THETA, OMEGA and SIGMA from a completed NONMEM run*

Description

Get THETA, OMEGA and SIGMA from a completed NONMEM run

Usage

```
nmxml(run = numeric(0), project = character(0), file = character(0),
  theta = TRUE, omega = TRUE, sigma = TRUE, olabels = NULL,
  slabels = NULL, oprefix = "", sprefix = "", tname = "THETA",
  oname = "...", sname = "...", index = "last", ...)
```

Arguments

run	run number
project	project directory
file	the complete path to the run.xml file
theta	logical; if TRUE, the $THETA vector is returned
omega	logical; if TRUE, the $OMEGA matrix is returned
sigma	logical; if TRUE, the $SIGMA matrix is returned
olabels	labels for $OMEGA
slabels	labels for $SIGMA
oprefix	prefix for $OMEGA labels
sprefix	prefix for $SIGMA labels
tname	name for $THETA
oname	name for $OMEGA
sname	name for $SIGMA
index	the estimation number to return; "last" will return the last estimation results; otherwise, pass an integer indicating which estimation results to return
...	not used

Details

If run and project are supplied, the .xml file is assumed to be located in run.xml, in directory run off the project directory. If file is supplied, run and project arguments are ignored.

This function requires that the xml2 package be installed and loadable. If requireNamespace("xml2") fails, an error will be generated.

Value

A list with theta, omega and sigma elements, depending on what was requested

Examples

```
if(requireNamespace("xml2")) {
  proj <- system.file("nonmem", package = "mrgsolve")
  mrgsolve:::nmxml(run = 1005, project = proj)
}
```

---

numerics_only *Prepare data.frame for input to mrgsim*

Description

Prepare data.frame for input to mrgsim

Usage

```
numerics_only(x, quiet = FALSE, convert_lgl = TRUE)
```

Arguments

x	a input data set
quiet	logical indicating whether or not warnings should be printed
convert_lgl	by default, convert logical columns with as.integer

---

obsaug *Augment observations in the simulated output*

Description

Augment observations in the simulated output

Usage

```
obsaug(x, value = TRUE, ...)
```

Arguments

x	model object
value	the value for obsaug
...	passed along There is also a obsaug argument to mrgsim that can be set to accomplish the same thing as a call to obsaug in the pipeline.

obsonly *Collect only observations in the simulated output*

Description

Collect only observations in the simulated output

Usage

```
obsonly(x, value = TRUE, ...)
```

Arguments

x	model object
value	the value for obsonly
...	passed along

Details

There is also a obsonly argument to mrgsim that can be set to accomplish the same thing as a call to obsonly in the pipeline.

omega *Manipulate OMEGA matrices*

Description

The primary function is omat that can be used to both get the $OMEGA matrices out of a model object and to update $OMEGA matrices in a model object.

Usage

```
omat(.x, ...)

## S4 method for signature 'missing'
omat(.x, ...)

## S4 method for signature 'matrix'
omat(.x, ..., labels = list())

## S4 method for signature '`NULL`'
omat(.x, ...)

## S4 method for signature 'list'
omat(.x, ...)
```

```
## S4 method for signature 'omegalist'
omat(.x, ...)

## S4 method for signature 'mrgmod'
omat(.x, ..., make = FALSE, open = FALSE)

## S4 method for signature 'mrgsims'
omat(.x, make = FALSE, ...)
```

Arguments

.x	a matrix, list of matrices or matlist object
...	passed to other functions, including modMATRIX
labels	character vector of names for $OMEGA elements; must be equal to number of rows/columns in the matrix
make	logical; if TRUE, matrix list is rendered into a single matrix
open	passed to merge.list
x	matlist object

Examples

```
## example("omega")
mat1 <- matrix(1)
mat2 <- diag(c(1,2,3))
mat3 <- matrix(c(0.1, 0.002, 0.002, 0.5), 2,2)
mat4 <- dmat(0.1, 0.2, 0.3, 0.4)

omat(mat1)
omat(mat1, mat2, mat3)
omat(A=mat1, B=mat2, C=mat3)

mod <- mrgsolve:::house() %>% omat(mat4)

omat(mod)
omat(mod, make=TRUE)


## Not run:

$OMEGA
1 2 3

$OMEGA @block
1 0.1 2

$OMEGA \@cor
\@ prefix ETA_
\@ labels CL VC KA
0.1
```

```
0.67 0.2
0 0 0.3


## End(Not run)
```

`param` *Create and work with parameter objects*

Description

See `numericlist` for methods to deal with `parameter_list` objects.

Usage

```
param(.x, ...)

## S4 method for signature 'mrgmod'
param(.x, .y = list(), ..., .pat = "*",
  .strict = FALSE)

## S4 method for signature 'mrgsims'
param(.x, ...)

## S4 method for signature 'missing'
param(..., .strict = TRUE)

## S4 method for signature 'list'
param(.x, ...)

## S4 method for signature 'ANY'
param(.x, ...)

allparam(.x)
```

Arguments

`.x`	the model object
`...`	passed along or name/value pairs to update the parameters in a model object
`.y`	list to be merged into parameter list
`.pat`	a regular expression (character) to be applied as a filter for which parameters to show when printing
`.strict`	if `TRUE`, all names to be updated must be found in the parameter list

Details

Can be used to either get a parameter list object from a mrgmod model object or to update the parameters in a model object. For both uses, the return value is a parameter_list object. For the former use, param is usually called to print the parameters to the screen, but the parameter_list object can also be coerced to a list or numeric R object.

Use allparam to get a parameter_list object including both model parameters and data items listed in $FIXED.

Value

An object of class parameter_list (see numericlist).

Examples

```
## example("param")

mod <- mrgsolve:::house()

param(mod)

param(mod, .pat="^(C|F)") ## may be useful when large number of parameters

class(param(mod))

param(mod)$KA

param(mod)[["KA"]]

as.list(param(mod))

as.data.frame(param(mod))

param(mod, CL = 1.2)

new_values <- list(CL = 1.3, VC = 20.5)

param(mod, new_values)
```

PKMODEL *Parse PKMODEL BLOCK data*

Description

Parse PKMODEL BLOCK data

Usage

```
PKMODEL(ncmt = 1, depot = FALSE, cmt = NULL,
  trans = pick_trans(ncmt, depot), env = list(), pos = 1, ...)
```

Arguments

ncmt	number of compartments; must be 1 (one-compartment, not including a depot dosing compartment) or 2 (two-compartment model, not including a depot dosing compartment)
depot	logical indicating whether to add depot compartment
cmt	compartment names as comma-delimited character
trans	the parameterization for the PK model; must be 1, 2, 4, or 11
env	parse environment
pos	block position number
...	not used

Details

When using $PKMODEL, certain symbols must be defined in the model specification depending on the value of ncmt, depot and trans.

- ncmt 1, depot FALSE, trans 2: CL, V
- ncmt 1, depot TRUE , trans 2: CL, V, KA
- ncmt 2, depot FALSE, trans 4: CL, V1, Q, V2
- ncmt 2, depot TRUE , trans 4: CL, V2, Q, V3, KA

If trans=11 is specified, use the symbols listed above for the ncmt / depot combination, but append i at the end (e.g. CLi or Qi or KAi).

If trans=1, the user must utilize the following symbols:

- pred_CL for clearance
- pred_V or pred_V2 for central compartment volume of distribution
- pred_Q for intercompartmental clearance
- pred_V3 for for peripheral compartment volume of distribution
- pred_KA for absorption rate constant

See Also

BLOCK_PARSE

plot,batch_mrgsims,missing-method *Plot method for mrgsims objects*

Description

Plot method for mrgsims objects

Usage

```
## S4 method for signature 'batch_mrgsims,missing'
plot(x, yval = variables(x),
  auto.key = list(), mincol = 3, ...)

## S4 method for signature 'batch_mrgsims,formula'
plot(x, y, show.grid = TRUE, lwd = 2,
  type = "l", yval = variables(x), auto.key = list(columns = 1),
  scales = list(y = list(relation = "free")), ...)
```

Arguments

x	mrgsims object
yval	y variables to plot
auto.key	passed to xyplot
mincol	minimum number of columns in key
...	arguments passed to xyplot
y	a formula passed to xyplot
show.grid	print grid in the plot
lwd	passed to xyplot
type	passed to xyplot
scales	passed to xyplot

plot_mrgsims *Generate a quick plot of simulated data*

Description

Generate a quick plot of simulated data

Usage

```
## S4 method for signature 'mrgsims,missing'
plot(x, limit = 16, ...)

## S4 method for signature 'mrgsims,formula'
plot(x, y, limit = 16, show.grid = TRUE,
  outer = TRUE, type = "l", lwd = 2, ylab = "value", groups = ID,
  scales = list(y = list(relation = "free")), logy = FALSE,
  logbr = 3, ...)
```

Arguments

x	mrgsims object
limit	limit the the number of panels to create
...	other arguments passed to xyplot
y	formula used for plotting
show.grid	logical indicating whether or not to draw panel.grid
outer	passed to xyplot
type	passed to xyplot
lwd	passed to xyplot
ylab	passed to xyplot
groups	passed to xyplot
scales	passed to xyplot
logy	plot the y variables on log scale
logbr	log scale breaks indicator; use 1 for breaks every log unit; use 3 for breaks every half log unit; use 0 for default breaks

Examples

```
mod <- mrgsolve:::house(end=48, delta=0.2) %>% init(GUT=1000)

out <- mrgsim(mod)

plot(out)

plot(out, subset=time <=24)

plot(out, GUT+CP~.)

plot(out, CP+RESP~time, col="black", scales="same", lty=2)
```

`plot_sims` *Plot data as an mrgsims object*

Description

Plot data as an mrgsims object

Usage

```
plot_sims(.data, ..., .f = NULL, .dots = list())
```

Arguments

`.data`	a data frame
`...`	unquoted column names to plot on y-axis
`.f`	a formula to plot
`.dots`	extra arguments passed to `lattice::xyplot`

Details

This function is only intended for use with data frames that were created by modifying an `mrgsims` object.

Examples

```
mod <- mrgsolve:::house() %>% ev(amt = 100)

out <- mrgsim(mod)
out_df <- dplyr::mutate(out, time <= 72)

plot(out)
plot_sims(out, CP, RESP)

## Not run:
plot_sims(out, .f = ~ CP + RESP)
plot_sims(out, .f = CP + RESP ~ time)

## End(Not run)
```

read_nmext *Extract estimates from NONMEM ext file*

Description

Extract estimates from NONMEM ext file

Usage

```
read_nmext(run, project = getwd(), file = paste0(run, ".ext"),
  path = NULL)
```

Arguments

run	a run number or run identifier
project	the NONMEM project directory
file	the ext file name
path	full path and file name for ext file

Value

A list with param, omega, and sigma in a format ready to be used to update a model object.

Examples

```
project <- system.file("nonmem", package = "mrgsolve")

est <- read_nmext(1005, project = project)

est$param

est$omega

est$sigma
```

realize_addl *Make addl doses explicit in an event object or data set*

Description

Make addl doses explicit in an event object or data set

Usage

```
realize_addl(x, ...)

## S3 method for class 'data.frame'
realize_addl(x, warn = FALSE, mark_new = FALSE,
  fill = c("inherit", "na", "locf"), ...)

## S3 method for class 'ev'
realize_addl(x, ...)
```

Arguments

x	a data_set data frame or an ev object (see details)
...	not used
warn	if TRUE a warning is issued if no ADDL or addl column is found
mark_new	if TRUE, a flag is added to indicate new columns
fill	specifies how to handle non-dose related data columns in new data set records; this option is critical when handling data sets with time-varying, non-dose-related data items; see details

Details

If no addl column is found the data frame is returned and a warning is issued if warn is true. If ii, time, or evid are missing, an error is generated.

Use caution when passing in data that has non-dose-related data columns that vary within a subject and pay special attention to the fill argument. By definition, realize_addl will add new rows to your data frame and it is not obvious how the non-dose-related data should be handled in these new rows. When inherit is chosen, the new records have non-dose-related data that is identical to the originating dose record. This should be fine when these data items are not varying with time, but will present a problem when the data are varying with time. When locf is chosen, the missing data are filled in with NA and an last observation carry forward operation is applied to **every** column in the data set. This may not be what you want if you already had missing values in the input data set and want to preserve that missingness. When na is chosen, the missing data are filled in with NA and no locf operation is applied. But note that these missing values may be problematic for a mrgsolve simulation run. If you have any time-varying columns or missing data in your data set, be sure to check that the output from this function is what you were expecting.

---

render *Render a model to a document*

Description

Render a model to a document

Usage

```
render(x, ...)

## S4 method for signature 'character'
render(x, project = NULL, ...)

## S4 method for signature 'mrgmod'
render(x, ...)

dorender(model, project, template = NULL, compile = TRUE, ...)
```

Arguments

x	model object or the model name
...	passed to rmarkdown::render
project	the directory containing the .cpp model file
model	model name
template	template document
compile	logical; if true, the model will be compiled to run

Examples

```
## Not run:
mod <- mrgsolve:::house()
mrgsolve:::render(mod)
mrgsolve:::render("irm2", modlib())

## End(Not run)
```

Req *Request simulated output*

Description

Use this function to select, by name, either compartments or derived variables that have been captured (see CAPTURE) into the simulated output.

Usage

```
Req(x, ...)

## S4 method for signature 'mrgmod'
Req(x, ...)

req(x, ...)
```

```
## S4 method for signature 'mrgmod'
req(x, ...)
```

Arguments

x	model object
...	unquoted names of compartments or tabled items

Details

There is also a Req argument to mrgsim that can be set to accomplish the same thing as a call to Req in the pipeline.

Note the difference between req and Req: the former only selects compartments to appear in output while the latter selects both compartments and captured items. Also, when there are items are explicitly listed in Req, all other compartments or captured items not listed there are ignored. But when compartments are selected with req all of the captured items are returned. Remember that req is strictly for compartments.

Examples

```
mod <- mrgsolve:::house()

mod %>% Req(CP,RESP) %>% ev(amt=1000) %>%  mrgsim
```

---

reserved *Reserved words*

Description

Reserved words

Usage

```
reserved()
```

Details

Note: this function is not exported; you must go into the mrgsolve namespace by using the mrgsolve::: prefix.

Examples

```
mrgsolve:::reserved()
```

revar *Get model random effect variances and covariances*

Description

Get model random effect variances and covariances

Usage

```
revar(x, ...)

## S4 method for signature 'mrgmod'
revar(x, ...)
```

Arguments

x	model object
...	passed along

see *Print model code to the console*

Description

Print model code to the console

Usage

```
see(x, ...)

## S4 method for signature 'mrgmod'
see(x, raw = FALSE, ...)
```

Arguments

x	model object
...	passed along
raw	return the raw code

Value

invisible NULL

sigma *Manipulate SIGMA matrices*

Description

The primary function is smat that can be used to both get the $SIGMA matrices out of a model object and to update $SIGMA matrices in a model object.

Usage

```
smat(.x, ...)

## S4 method for signature 'missing'
smat(.x, ...)

## S4 method for signature 'matrix'
smat(.x, ..., labels = list())

## S4 method for signature 'list'
smat(.x, ...)

## S4 method for signature 'sigmalist'
smat(.x, ...)

## S4 method for signature 'mrgmod'
smat(.x, ..., make = FALSE, open = FALSE)

## S4 method for signature '`NULL`'
smat(.x, ...)

## S4 method for signature 'mrgsims'
smat(.x, make = FALSE, ...)
```

Arguments

.x	a matrix, list of matrices or matlist object
...	passed to other functions, including modMATRIX
labels	character vector of names for $SIGMA elements; must be equal to number of rows/columns in the matrix
make	logical; if TRUE, matrix list is rendered into a single matrix
open	passed to merge.list
x	matlist object

Examples

```
## example("sigma")
mat1 <- matrix(1)
mat2 <- diag(c(1,2))
mat3 <- matrix(c(0.1, 0.002, 0.002, 0.5), 2,2)
mat4 <- dmat(0.1, 0.2, 0.3, 0.4)

smat(mat1)
smat(mat1, mat2, mat3)
smat(A=mat1, B=mat2, C=mat3)

mod <- mrgsolve:::house() %>% smat(mat1)

smat(mod)
smat(mod, make=TRUE)
```

---

simargs *Access or clear arguments for calls to mrgsim*

Description

Access or clear arguments for calls to mrgsim

Usage

```
simargs(x, which = NULL, clear = FALSE, ...)
```

Arguments

x	model object
which	character with length 1 naming a single arg to get
clear	logical indicating whether or not to clear args from the model object
...	passed along

Value

If clear is TRUE, the argument list is cleared and the model object is returned. Otherwise, the argument list is returned.

Examples

```
mod <- mrgsolve:::house()
mod %>% Req(CP,RESP) %>% carry_out(evid,WT,FLAG) %>% simargs
```

soloc *Return the location of the model shared object*

Description

Return the location of the model shared object

Usage

```
soloc(x, short = FALSE)
```

Arguments

x	model object
short	logical; if TRUE, soloc will be rendered with a short path name

Examples

```
mod <- mrgsolve:::house()
soloc(mod)
```

solversettings *Optional inputs for DLSODA*

Description

These are settings for the differential equation solver (DLSODA) that can be accessed via the R interface. The code listing below is taken directly from the DLSODA source code.

Details

The following items can be set

- hmax (HMAX below); decrease hmax when you want to limit how big of a step the solver can take when integrating from one time to the next time. However be aware that smaller hmax will result in longer run times.
- hmin (HMIN below); don't fiddle with this unless you know what you're doing.
- ixpr (IXPR below)
- maxsteps (MXSTEP below); increase this number when the solver has a long interval between two integration times (e.g. when observation records are far apart).
- mxhnil (MXHNIL below); don't usually modify this one

- `atol` - the absolute solver tolerance; decrease this number (e.g. to 1E-10 or 1E-20 or 1E-50) when the value in a compartment can get extremely small; without this extra (lower) tolerance, the value can get so low that the number can randomly become negative. However be aware that more precision here will result in longer run times.
- `rtol` - the relative solver tolerances; decrease this number when you want a more precise solution. However be aware that more precision here will result in longer run times.

Solver Settings

```
C-----------------------------------------------------------------------
C Optional Inputs.
C
C The following is a list of the optional inputs provided for in the
C call sequence.  (See also Part 2.)  For each such input variable,
C this table lists its name as used in this documentation, its
C location in the call sequence, its meaning, and the default value.
C The use of any of these inputs requires IOPT = 1, and in that
C case all of these inputs are examined.  A value of zero for any
C of these optional inputs will cause the default value to be used.
C Thus to use a subset of the optional inputs, simply preload
C locations 5 to 10 in RWORK and IWORK to 0.0 and 0 respectively, and
C then set those of interest to nonzero values.
C
C Name    Location      Meaning and Default Value
C
C
C HMAX    RWORK(6)  the maximum absolute step size allowed.
C                   The default value is infinite.
C
C HMIN    RWORK(7)  the minimum absolute step size allowed.
C                   The default value is 0.  (This lower bound is not
C                   enforced on the final step before reaching TCRIT
C                   when ITASK = 4 or 5.)
C
C IXPR    IWORK(5)  flag to generate extra printing at method switches.
C                   IXPR = 0 means no extra printing (the default).
C                   IXPR = 1 means print data on each switch.
C                   T, H, and NST will be printed on the same logical
C                   unit as used for error messages.
C
C MXSTEP  IWORK(6)  maximum number of (internally defined) steps
C                   allowed during one call to the solver.
C                   The default value is 500.
C
C MXHNIL  IWORK(7)  maximum number of messages printed (per problem)
C                   warning that T + H = T on a step (H = step size).
C                   This must be positive to result in a non-default
C                   value.  The default value is 10.
```

```
C
C-------------------------------------------------------------------------
```

See Also

aboutsolver, update

`tscale` *Re-scale time in the simulated output*

Description

Re-scale time in the simulated output

Usage

```
tscale(x, value = 1, ...)
```

Arguments

`x`	model object
`value`	value by which time will be scaled
`...`	passed along

Details

There is also a `tscale` argument to `mrgsim` that can be set to accomplish the same thing as a call to `tscale` in the pipeline.

Examples

```
# The model is in hours:
mod <- mrgsolve:::house()

# The output is in days:
mod %>% tscale(1/24) %>% mrgsim
```

update *Update the model object*

Description

After the model object is created, update various attributes.

Usage

```
## S4 method for signature 'mrgmod'
update(object, ..., merge = TRUE, open = FALSE,
  data = NULL)

## S4 method for signature 'omegalist'
update(object, y, ...)

## S4 method for signature 'sigmalist'
update(object, y, ...)

## S4 method for signature 'parameter_list'
update(object, .y, ...)

## S4 method for signature 'ev'
update(object, y, ...)
```

Arguments

object	a model object
...	named items to update
merge	logical indicating to merge (rather than replace) new and existing attributes
open	logical; used only when merge is TRUE and parameter list or initial conditions list is being updated; if FALSE, no new items will be added; if TRUE, the parameter list may expand.
data	a list of items to update; this list is combined with any items passed in via ...
y	another object involved in update
.y	data to update

Details

Slots that can be updated:

- verbose
- debug
- preclean
- mindt

- digits
- atol - absolute solver tolerance; see solversettings
- rtol - relative solver tolerance; see solversettings
- ixpr - see IXPR in solversettings
- mxhnil - see MXHNIL in solversettings
- hmin - see HMIN in solversettings
- hmax - see HMAX in solversettings
- maxsteps - see MXSTEP in solversettings
- start, end, delta, add
- tscale
- request
- param
- init
- omega
- sigma

Value

The updated model object is returned.

See Also

update, mrgmod-class

Examples

```
## Not run:
 mod <- mrgsolve:::house()

 mod <- update(mod, end=120, delta=4, param=list(CL=19.1))

## End(Not run)
```

---

valid_data_set *Validate and prepare a data sets for simulation*

Description

This function is called by mrgsim. Users may also call this function to pre-validate data when the same data set is used for repeated simulation.

Usage

```
valid_data_set(x, m = NULL, verbose = FALSE, quiet = FALSE)

valid_data_set.matrix(x, verbose = FALSE)
```

Arguments

x	data.frame or matrix
m	a model object
verbose	logical
quiet	if TRUE, messages will be suppressed

Value

A matrix with non-numeric columns dropped; if x is a data.frame with character cmt column comprised of valid compartment names and m is a model object, the cmt column will be converted to the corresponding compartment number.

See Also

valid_idata_set, idata_set, data_set

Examples

```
mod <- mrgsolve:::house()

data(exTheoph)

valid_data_set(exTheoph,mod)
```

---

valid_idata_set *Validate and prepare idata data sets for simulation*

Description

Validate and prepare idata data sets for simulation

Usage

```
valid_idata_set(x, m, verbose = FALSE, quiet = FALSE)
```

Arguments

x	data.frame or matrix
m	a model object
verbose	logical
quiet	if TRUE, messages will be suppressed

Value

A numeric matrix with class valid_idata_set.

See Also

valid_data_set, idata_set, data_set

$,mrgmod-method *Select parameter values from a model object*

Description

The $ and [[operators get the value of a single parameter in the model. The [gets several values, returning a named list.

Usage

```
## S4 method for signature 'mrgmod'
x$name

## S4 method for signature 'mrgmod'
x[[i, exact = TRUE]]

## S4 method for signature 'mrgmod'
x[i]
```

Arguments

x	mrgmod object
name	parameter to take
i	an element to select
exact	not used

Index